

Package ‘NetSimR’

January 18, 2023

Type Package

Title Actuarial Functions for Non-Life Insurance Modelling

Version 0.1.2

Author Yiannis Parizas [aut, cre]

Maintainer Yiannis Parizas <yiannis.parizas@gmail.com>

Description Assists actuaries and other insurance modellers in pricing, reserving and capital modelling for non-life insurance and reinsurance modelling. Provides functions that help model excess levels, capping and pure Incurred but not reported claims (pure IBNR).
Includes capped mean, exposure curves and increased limit factor curves (ILFs) for LogNormal, Gamma, Pareto, Sliced LogNormal-Pareto and Sliced Gamma-Pareto distributions.
Includes mean, probability density function (pdf), cumulative probability function (cdf) and inverse cumulative probability function for Sliced LogNormal-Pareto and Sliced Gamma-Pareto distributions.
Includes calculating pure IBNR exposure with LogNormal and Gamma distribution for reporting delay.
Includes a shiny tool to simulate insurance claims.

License GPL-3

Encoding UTF-8

Imports rmarkdown, shiny, shinybusy, future.apply, scales, future, methods

Suggests knitr, crch, testthat

VignetteBuilder knitr

RoxygenNote 7.2.3

NeedsCompilation no

Repository CRAN

Date/Publication 2023-01-17 23:10:02 UTC

R topics documented:

apply_deductible_limit	3
apply_severity_cap	3
distributionClass-class	4
dSlicedGammaPareto	4
dSlicedLNormPareto	5
erf	6
ExposureCurveGamma	6
ExposureCurveLNorm	7
ExposureCurvePareto	8
ExposureCurveSlicedGammaPareto	8
ExposureCurveSlicedLNormPareto	9
freq_dist_options	10
freq_dist_parameter_placeholders	10
GammaCappedMean	11
IGamma	11
ILFGamma	12
ILFLNorm	13
ILFPareto	13
ILFSlicedGammaPareto	14
ILFSlicedLNormPareto	15
LNormCappedMean	16
max_number_of_pareto_slices	16
NetSimR	17
ParetoCappedMean	18
ParetoCappedMeanCalc	18
pSlicedGammaPareto	19
pSlicedLNormPareto	20
PureIBNRGamma	21
PureIBNRLNorm	22
qSlicedGammaPareto	23
qSlicedLNormPareto	24
reinsurance_structures_options	25
rpareto	25
run_shiny_simulator	26
sev_dist_options	26
sev_dist_parameter_placeholders	27
shiny_simulator_server	27
shiny_simulator_ui	28
simulate_function	28
SlicedGammaParetoCappedMean	30
SlicedGammaParetoMean	31
SlicedLNormParetoCappedMean	31
SlicedLNormParetoMean	32

`apply_deductible_limit`*Apply a deductible and limit to claims*

Description

Apply a deductible and limit to claims

Usage

```
apply_deductible_limit(  
  gross_claims_data,  
  reinsurance_structure,  
  deductible,  
  limit  
)
```

Arguments

<code>gross_claims_data</code>	A vector of Claims.
<code>reinsurance_structure</code>	The chosen reinsurance structure. Options are: 'No Reinsurance Structure', 'Unlimited Layer', 'Limited Layer', 'Exclude Layer'.
<code>deductible</code>	The deductible of the reinsurance structure.
<code>limit</code>	The limit of the reinsurance structure.

Value

The ceded claims for the structure, with the chosen deductible and limit.

Examples

```
apply_deductible_limit(c(100, 50, 20), 'Limited Layer', 40, 20)  
apply_deductible_limit(c(100, 50, 20), 'Limited Layer', 10, 30)
```

`apply_severity_cap` *Apply severity cap function*

Description

Apply severity cap function

Usage

```
apply_severity_cap(claims, severity_cap_boolean, severity_cap_amount)
```

Arguments

claims	A vector of Claims.
severity_cap_boolean	A variable that if true, the function will cap the claims, otherwise will just return them.
severity_cap_amount	The claim cap value.

Value

If severity_cap_boolean is true, then will return the minimum of severity_cap_amount or claims otherwise will return claims. The operation is vectorised.

distributionClass-class

The class of the distribution objects

Description

The class of the distribution objects

dSlicedGammaPareto

The probability density function (pdf) of a Sliced Gamma Pareto severity distribution

Description

The probability density function (pdf) of a Sliced Gamma Pareto severity distribution

Usage

dSlicedGammaPareto(x, GShape, GRate, SlicePoint, PShape)

Arguments

x	A positive real number - the claim amount where the probability density function (pdf) will be evaluated.
GShape	A positive real number - the shape parameter of the attritional Claim Severity's Gamma distribution.
GRate	A positive real number - the rate parameter of the attritional Claim Severity's Gamma distribution.
SlicePoint	A positive real number - the slice point and the scale parameter of the tail Claim Severity's Pareto distribution.
PShape	A positive real number - the shape parameter of the tail Claim Severity's Pareto distribution.

Value

The value of the probability density function (pdf) at x with an attritional claim Gamma distribution with parameters $GShape$ and $GRate$ and a large claim Pareto distribution with parameters $SlicePoint$ and $PShape$.

Examples

```
dSlicedGammaPareto(3000,1,0.0005,1000,1.2)
dSlicedGammaPareto(1000,1.1,0.0006,2000,1.6)
dSlicedGammaPareto(2000,1.2,0.0004,3000,1.4)
```

dSlicedLNormPareto	<i>The probability density function (pdf) of a Sliced LogNormal Pareto severity distribution</i>
--------------------	--

Description

The probability density function (pdf) of a Sliced LogNormal Pareto severity distribution

Usage

```
dSlicedLNormPareto(x, mu, sigma, SlicePoint, shape)
```

Arguments

x	A positive real number - the claim amount where the probability density function (pdf) will be evaluated.
μ	A real number - the first parameter of the attritional Claim Severity's LogNormal distribution.
σ	A positive real number - the second parameter of the attritional Claim Severity's LogNormal distribution.
$SlicePoint$	A positive real number - the slice point and the scale parameter of the Claim Severity's Pareto distribution.
$shape$	A positive real number - the shape parameter of the Claim Severity's Pareto distribution.

Value

The value of the probability density function (pdf) at x with an attritional claim LogNormal distribution with parameters μ and σ and a large claim Pareto distribution with parameters $SlicePoint$ and $shape$.

Examples

```
dSlicedLNormPareto(1200,6,1.5,1000,1.2)
dSlicedLNormPareto(4000,7,1.6,3000,1.4)
```

erf	<i>Error function</i>
-----	-----------------------

Description

Error function

Usage

erf(x)

Arguments

x	A real number.
---	----------------

Value

The value of the error function at x.

Examples

```
erf(0.1)
erf(0.5)
```

ExposureCurveGamma	<i>Exposure Curve from a Gamma severity distribution</i>
--------------------	--

Description

Exposure Curve from a Gamma severity distribution

Usage

ExposureCurveGamma(x, shape, rate)

Arguments

x	A positive real number - the claim amount where the exposure curve will be evaluated.
shape	A positive real number - the shape parameter of the Claim Severity's Gamma distribution.
rate	A positive real number - the rate parameter of the Claim Severity's Gamma distribution.

Value

The value of the Exposure curve at x with Claim Severity from a Gamma distribution with parameters shape and rate.

Examples

```
ExposureCurveGamma(700,1,0.0005)
ExposureCurveGamma(1000,1.5,0.0006)
```

ExposureCurveLNorm *Exposure Curve from LogNormal a severity distribution*

Description

Exposure Curve from LogNormal a severity distribution

Usage

```
ExposureCurveLNorm(x, mu, sigma)
```

Arguments

x	A positive real number - the claim amount where the exposure curve will be evaluated.
mu	A real number - the first parameter of the Claim Severity's LogNormal distribution.
sigma	A positive real number - the second parameter of the Claim Severity's LogNormal distribution.

Value

The value of the Exposure curve at x with Claim Severity from a LogNormal distribution with parameters mu and sigma.

Examples

```
ExposureCurveLNorm(2000,6,1.5)
ExposureCurveLNorm(1000,5,1.6)
```

ExposureCurvePareto *Exposure Curve from a Pareto severity distribution*

Description

Exposure Curve from a Pareto severity distribution

Usage

ExposureCurvePareto(x, scale, shape)

Arguments

x	A positive real number - the claim amount where the exposure curve will be evaluated.
scale	A positive real number - the scale parameter of the Claim Severity's Pareto distribution.
shape	A positive real number - the shape parameter of the Claim Severity's Pareto distribution.

Value

The value of the Exposure curve at x with Claim Severity from a Pareto distribution with parameters scale and shape.

Examples

```
ExposureCurvePareto(700,500,1.2)
ExposureCurvePareto(20000,200,1.1)
```

ExposureCurveSlicedGammaPareto
 Exposure Curve from a Sliced Gamma Pareto severity distribution

Description

Exposure Curve from a Sliced Gamma Pareto severity distribution

Usage

ExposureCurveSlicedGammaPareto(x, GShape, GRate, SlicePoint, PShape)

Arguments

x	A positive real number - the claim amount where the exposure curve will be evaluated.
GShape	A positive real number - the shape parameter of the Claim Severity's Gamma distribution.
GRate	A positive real number - the rate parameter of the Claim Severity's Gamma distribution.
SlicePoint	A positive real number - the slice point and the scale parameter of the Claim Severity's Pareto distribution.
PShape	A positive real number - the shape parameter of the Claim Severity's Pareto distribution.

Value

The value of the Exposure curve at x with an attritional claim Gamma distribution with parameters GShape and GRate and a large claim Pareto distribution with parameters SlicePoint and PShape.

Examples

```
ExposureCurveSlicedGammaPareto(3000,1,0.0005,1000,1.2)
ExposureCurveSlicedGammaPareto(1000,1.1,0.0006,2000,1.6)
ExposureCurveSlicedGammaPareto(2000,1.2,0.0004,3000,1.4)
```

ExposureCurveSlicedLNormPareto

Exposure Curve from a Sliced LogNormal Pareto severity distribution

Description

Exposure Curve from a Sliced LogNormal Pareto severity distribution

Usage

```
ExposureCurveSlicedLNormPareto(x, mu, sigma, SlicePoint, shape)
```

Arguments

x	A positive real number - the claim amount where the exposure curve will be evaluated.
mu	A real number - the first parameter of the attritional Claim Severity's LogNormal distribution.
sigma	A positive real number - the second parameter of the attritional Claim Severity's LogNormal distribution.
SlicePoint	A positive real number - the slice point and the scale parameter of the tail Claim Severity's Pareto distribution.
shape	A positive real number - the shape parameter of the tail Claim Severity's Pareto distribution.

Value

The value of the Exposure curve at x with an attritional claim LogNormal distribution with parameters μ and σ and a large claim Pareto distribution with parameters SlicePoint and shape .

Examples

```
ExposureCurveSlicedLNormPareto(1200,6,1.5,1000,1.2)
ExposureCurveSlicedLNormPareto(4000,7,1.6,3000,1.4)
```

freq_dist_options *A vector with the frequency distribution objects*

Description

A vector with the frequency distribution objects

Usage

```
freq_dist_options
```

Format

An object of class `list` of length 4.

Value

The frequency distribution objects.

freq_dist_parameter_placeholders
A data frame with the frequency distribution parameter placeholders

Description

A data frame with the frequency distribution parameter placeholders

Usage

```
freq_dist_parameter_placeholders
```

Format

An object of class `data.frame` with 2 rows and 2 columns.

Value

The frequency distribution parameter placeholders.

GammaCappedMean	<i>Gamma capped mean</i>
-----------------	--------------------------

Description

Gamma capped mean

Usage

GammaCappedMean(cap, shape, rate)

Arguments

cap	A positive real number - the claim severity cap.
shape	A positive real number - the shape parameter of the Claim Severity's Gamma distribution.
rate	A positive real number - the rate parameter of the Claim Severity's Gamma distribution.

Value

The mean of the claim severity capped at cap with a Gamma distribution with parameters shape and rate.

Examples

```
GammaCappedMean(700, 1, 0.0005)
GammaCappedMean(1000, 1.5, 0.0006)
```

IGamma	<i>Lower incomplete gamma function</i>
--------	--

Description

Lower incomplete gamma function

Usage

IGamma(a, x)

Arguments

a	A positive real number.
x	A positive real number.

Value

The value of the lower incomplete gamma function at x with shape parameter a.

Examples

```
IGamma(1,1)
IGamma(0.1,2)
```

ILFGamma

Increased Limit Factor Curve from a Gamma severity distribution

Description

Increased Limit Factor Curve from a Gamma severity distribution

Usage

```
ILFGamma(xLow, xHigh, shape, rate)
```

Arguments

xLow	A positive real number - the claim amount where the Increased Limit Factor Curve will be evaluated from.
xHigh	A positive real number - the claim amount where the Increased Limit Factor Curve will be evaluated to.
shape	A positive real number - the shape parameter of the Claim Severity's Gamma distribution.
rate	A positive real number - the rate parameter of the Claim Severity's Gamma distribution.

Value

The value of the Increased Limit Factor curve from xLow to xHigh with Claim Severity from a Gamma distribution with parameters shape and rate.

Examples

```
ILFGamma(1000,700,1,0.0005)
ILFGamma(1200,1000,1.5,0.0006)
```

ILFLNorm	<i>Increased Limit Factor Curve from a LogNormal severity distribution</i>
----------	--

Description

Increased Limit Factor Curve from a LogNormal severity distribution

Usage

ILFLNorm(xLow, xHigh, mu, sigma)

Arguments

xLow	A positive real number - the claim amount where the Increased Limit Factor Curve will be evaluated from.
xHigh	A positive real number - the claim amount where the Increased Limit Factor Curve will be evaluated to.
mu	A real number - the first parameter of the Claim Severity's LogNormal distribution.
sigma	A positive real number - the second parameter of the Claim Severity's LogNormal distribution.

Value

The value of the Increased Limit Factor curve from xLow to xHigh with Claim Severity from a LogNormal distribution with parameters mu and sigma.

Examples

```
ILFLNorm(1000,2000,6,1.5)
ILFLNorm(1000,1500,5,1.6)
```

ILFPareto	<i>Increased Limit Factor Curve from a Pareto severity distribution</i>
-----------	---

Description

Increased Limit Factor Curve from a Pareto severity distribution

Usage

ILFPareto(xLow, xHigh, scale, shape)

Arguments

xLow	A positive real number - the claim amount where the Increased Limit Factor Curve will be evaluated from.
xHigh	A positive real number - the claim amount where the Increased Limit Factor Curve will be evaluated to.
scale	A positive real number - the scale parameter of the Claim Severity's Pareto distribution.
shape	A positive real number - the shape parameter of the Claim Severity's Pareto distribution.

Value

The value of the Increased Limit Factor curve from xLow to xHigh with Claim Severity from a Pareto distribution with parameters scale and shape.

Examples

```
ILFPareto(700,1200,500,1.2)
ILFPareto(1200,20000,200,1.1)
```

ILFSlicedGammaPareto *Increased Limit Factor Curve from a Sliced Gamma Pareto severity distribution*

Description

Increased Limit Factor Curve from a Sliced Gamma Pareto severity distribution

Usage

```
ILFSlicedGammaPareto(xLow, xHigh, GShape, GRate, SlicePoint, PShape)
```

Arguments

xLow	A positive real number - the claim amount where the Limit Factor Curve will be evaluated from.
xHigh	A positive real number - the claim amount where the Limit Factor Curve will be evaluated to.
GShape	A positive real number - the shape parameter of the attritional Claim Severity's Gamma distribution.
GRate	A positive real number - the rate parameter of the attritional Claim Severity's Gamma distribution.
SlicePoint	A positive real number - the slice point and the scale parameter of the tail Claim Severity's Pareto distribution.
PShape	A positive real number - the shape parameter of the tail Claim Severity's Pareto distribution.

Value

The value of the Increased Limit Factor curve from xLow to xHigh with an attritional claim Gamma distribution with parameters GShape and GRate and a large claim Pareto distribution with parameters SlicePoint and PShape.

Examples

```
ILFSlicedGammaPareto(2000,3000,1,0.0005,1000,1.2)
ILFSlicedGammaPareto(800,1000,1.1,0.0006,2000,1.6)
ILFSlicedGammaPareto(1200,2000,1.2,0.0004,3000,1.4)
```

ILFSlicedLNormPareto *Increased Limit Factor Curve from a Sliced LogNormal Pareto severity distribution*

Description

Increased Limit Factor Curve from a Sliced LogNormal Pareto severity distribution

Usage

```
ILFSlicedLNormPareto(xLow, xHigh, mu, sigma, SlicePoint, shape)
```

Arguments

xLow	A positive real number - the claim amount where the Limit Factor Curve will be evaluated from.
xHigh	A positive real number - the claim amount where the Limit Factor Curve will be evaluated to.
mu	A real number - the first parameter of the attritional Claim Severity's LogNormal distribution.
sigma	A positive real number - the second parameter of the attritional Claim Severity's LogNormal distribution.
SlicePoint	A positive real number - the slice point and the scale parameter of the tail Claim Severity's Pareto distribution.
shape	A positive real number - the shape parameter of the tail Claim Severity's Pareto distribution.

Value

The value of the Increased Limit Factor curve from xLow to xHigh with an attritional claim LogNormal distribution with parameters mu and sigma and a large claim Pareto distribution with parameters SlicePoint and shape.

Examples

```
ILFSlicedLNormPareto(800,1200,6,1.5,1000,1.2)
ILFSlicedLNormPareto(2000,4000,7,1.6,3000,1.4)
```

LNormCappedMean	<i>Lognormal capped mean</i>
-----------------	------------------------------

Description

Lognormal capped mean

Usage

```
LNormCappedMean(cap, mu, sigma)
```

Arguments

cap	A positive real number - the claim severity cap.
mu	A real number - the first parameter of the Claim Severity's LogNormal distribution.
sigma	A positive real number - the second parameter of the Claim Severity's LogNormal distribution.

Value

The mean of the claim severity capped at cap with a LogNormal distribution with parameters mu and sigma.

Examples

```
LNormCappedMean(2000,6,1.5)
LNormCappedMean(1000,5,1.6)
```

max_number_of_pareto_slices

Parameter to set the maximum number of pareto slices

Description

Parameter to set the maximum number of pareto slices

Usage

```
max_number_of_pareto_slices
```

Format

An object of class numeric of length 1.

Value

The the maximum number of Pareto Slices.

NetSimR	<i>NetSimR: A non-life insurance package for computing various statistics.</i>
---------	--

Description

The NetSimR package provides three categories of functions:

1. Capped means, Exposure and ILF curve from various severity distributions
2. Pure IBNR and UPR earned periods
3. Sliced distributions

NetSimR mean functions

[SlicedGammaParetoMean](#) [SlicedLNormParetoMean](#)

NetSimR capped mean functions

[GammaCappedMean](#) [LNormCappedMean](#) [ParetoCappedMean](#) [SlicedGammaParetoCappedMean](#) [SlicedLNormParetoCappedMean](#)

NetSimR exposure curve functions

[ExposureCurveGamma](#) [ExposureCurveLNorm](#) [ExposureCurvePareto](#) [ExposureCurveSlicedGammaPareto](#)
[ExposureCurveSlicedLNormPareto](#)

NetSimR ILF curve functions

[ILFGamma](#) [ILFLNorm](#) [ILFPareto](#) [ILFSlicedGammaPareto](#) [ILFSlicedLNormPareto](#)

NetSimR pure IBNR functions

[PureIBNRGamma](#) [PureIBNRLNorm](#)

NetSimR Sliced distribution functions

[dSlicedGammaPareto](#) [dSlicedLNormPareto](#) [pSlicedGammaPareto](#) [pSlicedLNormPareto](#) [qSlicedGammaPareto](#)
[qSlicedLNormPareto](#)

ParetoCappedMean *Pareto capped mean*

Description

Pareto capped mean

Usage

ParetoCappedMean(cap, scale, shape)

Arguments

cap	A positive real number - the claim severity cap.
scale	A positive real number - the scale parameter of the Claim Severity's Pareto distribution.
shape	A positive real number - the shape parameter of the Claim Severity's Pareto distribution.

Value

The mean of the claim severity capped at cap with a Pareto distribution with parameters scale and shape.

Examples

```
ParetoCappedMean(600,200,1.2)
ParetoCappedMean(800,100,1)
ParetoCappedMean(1000,500,0.8)
```

ParetoCappedMeanCalc *Pareto capped mean intermediary calculation*

Description

Pareto capped mean intermediary calculation

Usage

ParetoCappedMeanCalc(cap, scale, shape)

Arguments

cap	A positive real number - the claim severity cap.
scale	A positive real number - the scale parameter of the Claim Severity's Pareto distribution.
shape	A positive real number - the shape parameter of the Claim Severity's Pareto distribution.

Value

An interim calculation for the mean of the claim severity capped at cap with a Pareto distribution with parameters scale and shape.

Examples

```
ParetoCappedMeanCalc(800,100,1.1)
ParetoCappedMeanCalc(1000,500,0.9)
```

pSlicedGammaPareto	<i>The cumulative density function (cdf) of a Sliced Gamma-Pareto severity distribution</i>
--------------------	---

Description

The cumulative density function (cdf) of a Sliced Gamma-Pareto severity distribution

Usage

```
pSlicedGammaPareto(x, GShape, GRate, SlicePoint, PShape)
```

Arguments

x	A positive real number - the claim amount where the cumulative density function (cdf) will be evaluated.
GShape	A positive real number - the shape parameter of the attritional Claim Severity's Gamma distribution.
GRate	A positive real number - the rate parameter of the attritional Claim Severity's Gamma distribution.
SlicePoint	A positive real number - the slice point and the scale parameter of the tail Claim Severity's Pareto distribution.
PShape	A positive real number - the shape parameter of the tail Claim Severity's Pareto distribution.

Value

The value of the cumulative density function (cdf) at x with an attritional claim Gamma distribution with parameters GShape and GRate and a large claim Pareto distribution with parameters SlicePoint and PShape.

Examples

```
pSlicedGammaPareto(3000,1,0.0005,1000,1.2)
pSlicedGammaPareto(1000,1.1,0.0006,2000,1.6)
pSlicedGammaPareto(2000,1.2,0.0004,3000,1.4)
```

pSlicedLNormPareto *The cumulative density function (cdf) of a Sliced LogNormal Pareto severity distribution*

Description

The cumulative density function (cdf) of a Sliced LogNormal Pareto severity distribution

Usage

```
pSlicedLNormPareto(x, mu, sigma, SlicePoint, shape)
```

Arguments

x	A positive real number - the claim amount where the cumulative density function (cdf) will be evaluated.
mu	A real number - the first parameter of the attritional Claim Severity's LogNormal distribution.
sigma	A positive real number - the second parameter of the attritional Claim Severity's LogNormal distribution.
SlicePoint	A positive real number - the slice point and the scale parameter of the tail Claim Severity's Pareto distribution.
shape	A positive real number - the shape parameter of the tail Claim Severity's Pareto distribution.

Value

The value of the cumulative density function (cdf) at x with an attritional claim LogNormal distribution with parameters mu and sigma and a large claim Pareto distribution with parameters SlicePoint and shape.

Examples

```
pSlicedLNormPareto(1200,6,1.5,1000,1.2)
pSlicedLNormPareto(4000,7,1.6,3000,1.4)
```

PureIBNRGamma	<i>Pure IBNR exposure from a Gamma reporting delay distribution</i>
---------------	---

Description

Pure IBNR exposure from a Gamma reporting delay distribution

Usage

```
PureIBNRGamma(IncDate, ExpDate, ValDate, shape, rate)
```

Arguments

IncDate	A date - the inception date of the period.
ExpDate	A date - the expiry date of the period. Must be greater than inception date.
ValDate	A date - the valuation date.
shape	A positive real number - the shape parameter of the reporting delay's Gamma distribution.
rate	A positive real number - the rate parameter of the reporting delay's Gamma distribution.

Value

Unearned and Pure IBNR exposure in days and as a percentage of the period's duration, where the reporting delay has a Gamma distribution with parameters shape and rate.

Examples

```
Dates = data.frame(
  inceptionDate = c("01/01/2006", "01/07/2006", "01/01/2007")
  ,expiryDate = c("31/12/2006", "30/06/2007", "31/12/2007")
)

Dates$inceptionDate<-as.POSIXct(Dates$inceptionDate, format="%d/%m/%Y")

Dates$expiryDate<-as.POSIXct(Dates$expiryDate, format="%d/%m/%Y")

ValuationDate<-as.POSIXct("30/10/2007", format="%d/%m/%Y")

PureIBNRGamma(Dates$inceptionDate,Dates$expiryDate,ValuationDate,7,0.15)
```

 PureIBNRLNorm

Pure IBNR exposure from a LogNormal reporting delay distribution

Description

Pure IBNR exposure from a LogNormal reporting delay distribution

Usage

```
PureIBNRLNorm(IncDate, ExpDate, ValDate, mu, sigma)
```

Arguments

IncDate	A date - the inception date of the period.
ExpDate	A date - the expiry date of the period. Must be greater than inception date.
ValDate	A date - the valuation date.
mu	A real number - the first parameter of the reporting delay's LogNormal distribution.
sigma	A positive real number - the second parameter of the reporting delay's LogNormal distribution.

Value

Unearned and Pure IBNR exposure in days and as a percentage of the period's duration, where the reporting delay has a LogNormal distribution with parameters mu and sigma.

Examples

```
Dates = data.frame(
  inceptionDate = c("01/01/2006", "01/07/2006", "01/01/2007")
  ,expiryDate = c("31/12/2006", "30/06/2007", "31/12/2007")
)

Dates$inceptionDate<-as.POSIXct(Dates$inceptionDate, format="%d/%m/%Y")

Dates$expiryDate<-as.POSIXct(Dates$expiryDate, format="%d/%m/%Y")

ValuationDate<-as.POSIXct("30/10/2007", format="%d/%m/%Y")

PureIBNRLNorm(Dates$inceptionDate,Dates$expiryDate,ValuationDate,4,1.5)
```

qSlicedGammaPareto	<i>The inverse cumulative density function of a Sliced Gamma Pareto severity distribution</i>
--------------------	---

Description

The inverse cumulative density function of a Sliced Gamma Pareto severity distribution

Usage

```
qSlicedGammaPareto(q, GShape, GRate, SlicePoint, PShape)
```

Arguments

q	A real number between 0 and 1 - the probability where the inverse cumulative density function will be evaluated.
GShape	A positive real number - the shape parameter of the attritional Claim Severity's Gamma distribution.
GRate	A positive real number - the rate parameter of the attritional Claim Severity's Gamma distribution.
SlicePoint	A positive real number - the slice point and the scale parameter of the tail Claim Severity's Pareto distribution.
PShape	A positive real number - the shape parameter of the tail Claim Severity's Pareto distribution.

Value

The value of the inverse cumulative density function at q with an attritional claim Gamma distribution with parameters GShape and GRate and a large claim Pareto distribution with parameters SlicePoint and PShape.

Examples

```
qSlicedGammaPareto(0.5,1,0.0005,1000,1.2)
qSlicedGammaPareto(0.2,1.1,0.0006,2000,1.6)
qSlicedGammaPareto(0.8,1.2,0.0004,3000,1.4)
```

qSlicedLNormPareto	<i>The inverse cumulative density function of a Sliced LogNormal Pareto severity distribution</i>
--------------------	---

Description

The inverse cumulative density function of a Sliced LogNormal Pareto severity distribution

Usage

```
qSlicedLNormPareto(q, mu, sigma, SlicePoint, shape)
```

Arguments

q	A real number between 0 and 1 - the probability where the inverse cumulative density function will be evaluated.
mu	A real number - the first parameter of the attritional Claim Severity's LogNormal distribution.
sigma	A positive real number - the second parameter of the attritional Claim Severity's LogNormal distribution.
SlicePoint	A positive real number - the slice point and the scale parameter of the tail Claim Severity's Pareto distribution.
shape	A positive real number - the shape parameter of the tail Claim Severity's Pareto distribution.

Value

The value of the inverse cumulative density function at q with an attritional claim LogNormal distribution with parameters mu and sigma and a large claim Pareto distribution with parameters SlicePoint and shape.

Examples

```
qSlicedLNormPareto(0.5,6,1.5,1000,1.2)
qSlicedLNormPareto(0.7,7,1.6,3000,1.4)
```

reinsurance_structures_options

A vector with the reinsurance structure options

Description

A vector with the reinsurance structure options

Usage

```
reinsurance_structures_options
```

Format

An object of class character of length 4.

Value

The reinsurance structure options

rpareto

Random Pareto generator

Description

Random Pareto generator

Usage

```
rpareto(n, alpha, x_m)
```

Arguments

n	Number of values to generate.
alpha	A positive real number. Alpha parameter of the Pareto distribution.
x_m	A positive real number. The minimum value for the Pareto distribution.

Value

A vector of n random Pareto variables with parameters alpha and x_m.

run_shiny_simulator *A function to run the shiny simulator application*

Description

A function to run the shiny simulator application

Usage

```
run_shiny_simulator()
```

Value

Opens the shiny simulator application

sev_dist_options *A vector with the severity distribution objects*

Description

A vector with the severity distribution objects

Usage

```
sev_dist_options
```

Format

An object of class `list` of length 6.

Value

The severity distribution objects.

`sev_dist_parameter_placeholders`*A data frame with the severity distribution parameter placeholders*

Description

A data frame with the severity distribution parameter placeholders

Usage

```
sev_dist_parameter_placeholders
```

Format

An object of class `data.frame` with 2 rows and 2 columns.

Value

The severity distribution parameter placeholders.

`shiny_simulator_server`*Server function for the Shiny Simulator application*

Description

Server function for the Shiny Simulator application

Usage

```
shiny_simulator_server(input, output, session)
```

Arguments

<code>input</code>	Input for the server function.
<code>output</code>	Output for the server function.
<code>session</code>	Session for the server function.

Value

Returns server rendering for the shiny application.

shiny_simulator_ui	<i>UI file for the Shiny Simulator application</i>
--------------------	--

Description

UI file for the Shiny Simulator application

Usage

```
shiny_simulator_ui
```

Format

An object of class `shiny.tag.list` (inherits from `list`) of length 4.

Value

Returns the UI code for the shiny application.

simulate_function	<i>A function to simulate frequency - severity of insurance claims. The function applies severity cap, reinsurance structure for each and every loss claim, reinsurance structure for each and aggregate claims. The function allows for piecewise pareto slices.</i>
-------------------	---

Description

A function to simulate frequency - severity of insurance claims. The function applies severity cap, reinsurance structure for each and every loss claim, reinsurance structure for each and aggregate claims. The function allows for piecewise pareto slices.

Usage

```
simulate_function(  
  numOfSimulations,  
  freq_params,  
  sev_params,  
  seedSetBinary,  
  seedValue,  
  freqDistr,  
  sevDistr,  
  paretoSlice,  
  pareto_slice_times,  
  slice_pareto_alphas,  
  slice_pareto_x_ms,  
  sevCapBinary,
```

```

sev_cap_amount,
reinsuranceStructureEEL,
reinsurance_structure_eel_deductible_amount,
reinsurance_structure_eel_limit_amount,
reinsuranceStructureAL,
reinsurance_structure_al_deductible_amount,
reinsurance_structure_al_limit_amount,
reinsuranceStructureLimitedReinstatements,
reinsuranceStructureReinstatementLimit,
multiprocessing
)

```

Arguments

```

numOfSimulations      The number of simulations to run.
freq_params           A vector of the frequency distribution parameters.
sev_params            A vector of the severity distribution parameters.
seedSetBinary         True if there is a fixed seed, otherwise false.
seedValue             The seed value.
freqDistr             The frequency distribution. Options are as per the freq_dist_options.
sevDistr              The severity distribution. Options are as per the sev_dist_options.
paretoSlice          True if there is Pareto slicing.
pareto_slice_times    The number of Pareto slices.
slice_pareto_alphas   A vector of Pareto slices' alpha parameters.
slice_pareto_x_ms     A vector of Pareto slices' x_m parameters.
sevCapBinary         True if there is a severity cap.
sev_cap_amount       The severity cap amount.
reinsuranceStructureEEL
                    The chosen reinsurance structure for each and every loss claim.
reinsurance_structure_eel_deductible_amount
                    The deductible for each and every loss reinsurance structure.
reinsurance_structure_eel_limit_amount
                    The limit for each and every loss reinsurance structure.
reinsuranceStructureAL
                    The chosen reinsurance structure for aggregate claims.
reinsurance_structure_al_deductible_amount
                    The deductible for aggregate reinsurance structure.
reinsurance_structure_al_limit_amount
                    The limit for aggregate reinsurance structure.
reinsuranceStructureLimitedReinstatements
                    True if there is a limit in reinstatements, otherwise false.

```

reinsuranceStructureReinstatementLimit
 The reinstatement limit.

multiprocessing
 True if multiprocessing is used, otherwise false.

Value

A data frame with claims counts, ceded claims and the number of reinstatements used.

SlicedGammaParetoCappedMean
Sliced Gamma Pareto capped mean

Description

Sliced Gamma Pareto capped mean

Usage

SlicedGammaParetoCappedMean(cap, GShape, GRate, SlicePoint, PShape)

Arguments

cap A positive real number - the claim severity cap.

GShape A positive real number - the shape parameter of the attritional Claim Severity's Gamma distribution.

GRate A positive real number - the rate parameter of the attritional Claim Severity's Gamma distribution.

SlicePoint A positive real number - the slice point and the scale parameter of the tail Claim Severity's Pareto distribution.

PShape A positive real number - the shape parameter of the tail Claim Severity's Pareto distribution.

Value

The mean of the claim severity capped at cap with an attritional claim Gamma distribution with parameters GShape and GRate and a large claim Pareto distribution with parameters SlicePoint and PShape.

Examples

```
SlicedGammaParetoCappedMean(3000,1,0.0005,1000,1.2)
SlicedGammaParetoCappedMean(1000,1.1,0.0006,2000,1.6)
SlicedGammaParetoCappedMean(2000,1.2,0.0004,3000,1.4)
```

SlicedGammaParetoMean *Sliced Gamma Pareto mean*

Description

Sliced Gamma Pareto mean

Usage

SlicedGammaParetoMean(GShape, GRate, SlicePoint, PShape)

Arguments

GShape	A positive real number - the shape parameter of the attritional Claim Severity's Gamma distribution.
GRate	A positive real number - the rate parameter of the attritional Claim Severity's Gamma distribution.
SlicePoint	A positive real number - the slice point and the scale parameter of the tail Claim Severity's Pareto distribution.
PShape	A positive real number - the Shape parameter of the tail Claim Severity's Pareto distribution.

Value

The mean of the claim severity with an attritional claim Gamma distribution with parameters GShape and GRate and a large claim Pareto distribution with parameters SlicePoint and PShape.

Examples

```
SlicedGammaParetoMean(1,0.0005,1000,1.2)
SlicedGammaParetoMean(1.1,0.0006,2000,1.6)
SlicedGammaParetoMean(1.2,0.0004,3000,1.4)
```

SlicedLNormParetoCappedMean
Sliced LogNormal Pareto capped mean

Description

Sliced LogNormal Pareto capped mean

Usage

SlicedLNormParetoCappedMean(cap, mu, sigma, SlicePoint, shape)

Arguments

cap	A positive real number - the claim severity cap.
mu	A real number - the first parameter of the attritional Claim Severity's LogNormal distribution.
sigma	A positive real number - the second parameter of the attritional Claim Severity's LogNormal distribution.
SlicePoint	A positive real number - the slice point and the scale parameter of the tail Claim Severity's Pareto distribution.
shape	A positive real number - the shape parameter of the tail Claim Severity's Pareto distribution.

Value

The mean of the claim severity capped at cap with an attritional claim LogNormal distribution with parameters mu and sigma and a large claim Pareto distribution with parameters SlicePoint and shape.

Examples

```
SlicedLNormParetoCappedMean(1200, 6, 1.5, 1000, 1.2)
SlicedLNormParetoCappedMean(2500, 6.5, 1.4, 2000, 1.6)
SlicedLNormParetoCappedMean(4000, 7, 1.6, 3000, 1.4)
```

SlicedLNormParetoMean *Sliced LogNormal Pareto mean*

Description

Sliced LogNormal Pareto mean

Usage

```
SlicedLNormParetoMean(mu, sigma, SlicePoint, shape)
```

Arguments

mu	A real number - the first parameter of the attritional Claim Severity's LogNormal distribution.
sigma	A positive real number - the second parameter of the attritional Claim Severity's LogNormal distribution.
SlicePoint	A positive real number - the slice point and the scale parameter of the tail Claim Severity's Pareto distribution.
shape	A positive real number - the shape parameter of the tail Claim Severity's Pareto distribution.

Value

The mean of the claim severity with an attritional claim LogNormal distribution with parameters μ and σ and a large claim Pareto distribution with parameters *SlicePoint* and *shape*.

Examples

```
SlicedLNormParetoMean(6,1.5,1000,1.2)  
SlicedLNormParetoMean(6.5,1.4,2000,1.6)  
SlicedLNormParetoMean(7,1.6,3000,1.4)
```

Index

- * **datasets**
 - freq_dist_options, [10](#)
 - freq_dist_parameter_placeholders, [10](#)
 - max_number_of_pareto_slices, [16](#)
 - reinsurance_structures_options, [25](#)
 - sev_dist_options, [26](#)
 - sev_dist_parameter_placeholders, [27](#)
 - shiny_simulator_ui, [28](#)
- apply_deductible_limit, [3](#)
- apply_severity_cap, [3](#)
- distributionClass
 - (distributionClass-class), [4](#)
- distributionClass-class, [4](#)
- dSlicedGammaPareto, [4](#), [17](#)
- dSlicedLNormPareto, [5](#), [17](#)
- erf, [6](#)
- ExposureCurveGamma, [6](#), [17](#)
- ExposureCurveLNorm, [7](#), [17](#)
- ExposureCurvePareto, [8](#), [17](#)
- ExposureCurveSlicedGammaPareto, [8](#), [17](#)
- ExposureCurveSlicedLNormPareto, [9](#), [17](#)
- freq_dist_options, [10](#)
- freq_dist_parameter_placeholders, [10](#)
- GammaCappedMean, [11](#), [17](#)
- IGamma, [11](#)
- ILFGamma, [12](#), [17](#)
- ILFLNorm, [13](#), [17](#)
- ILFPareto, [13](#), [17](#)
- ILFSlicedGammaPareto, [14](#), [17](#)
- ILFSlicedLNormPareto, [15](#), [17](#)
- LNormCappedMean, [16](#), [17](#)
- max_number_of_pareto_slices, [16](#)
- NetSimR, [17](#)
- ParetoCappedMean, [17](#), [18](#)
- ParetoCappedMeanCalc, [18](#)
- pSlicedGammaPareto, [17](#), [19](#)
- pSlicedLNormPareto, [17](#), [20](#)
- PureIBNRGamma, [17](#), [21](#)
- PureIBNRLNorm, [17](#), [22](#)
- qSlicedGammaPareto, [17](#), [23](#)
- qSlicedLNormPareto, [17](#), [24](#)
- reinsurance_structures_options, [25](#)
- rpareto, [25](#)
- run_shiny_simulator, [26](#)
- sev_dist_options, [26](#)
- sev_dist_parameter_placeholders, [27](#)
- shiny_simulator_server, [27](#)
- shiny_simulator_ui, [28](#)
- simulate_function, [28](#)
- SlicedGammaParetoCappedMean, [17](#), [30](#)
- SlicedGammaParetoMean, [17](#), [31](#)
- SlicedLNormParetoCappedMean, [17](#), [31](#)
- SlicedLNormParetoMean, [17](#), [32](#)